

HW6

T1

The main program below calls a subroutine `F`. The `F` subroutine uses R3 and R4 as input, and produces an output which is placed in R0. The subroutine modifies registers R0, R3, R4, R5, and R6 in order to complete its task. `F` calls two other subroutines, `SaveRegisters` and `RestoreRegisters`, that are intended handle the saving and restoring of the modified registers (although we will see in question (b) that this may not be the best idea!).

```
1 ; Main Program;
2 .ORIG x3000
3 ...
4 ...
5 JSR F
6 ...
7 ...
8 HALT
9 ; R3 and R4 are input.
10 ; Modifies R0, R3, R4, R5, and R6
11 ; R0 is the output
12 ;
13 F
14 JSR SaveRegisters
15 ...
16 ...
17 ...
18 JSR RestoreRegisters
19 RET
20 .END
```

(a) Write the two subroutines `SaveRegisters` and `RestoreRegisters`.

(b) When we run the code we notice there is an infinite loop. Why? What small change can we make to our program to correct this error. Please specify both the correction and the subroutine that is being corrected.

T2

Assume that you have the following table in your program:

```
1 MASKS
2 .FILL x0001
3 .FILL x0002
4 .FILL x0004
5 .FILL x0008
6 .FILL x0010
7 .FILL x0020
8 .FILL x0040
9 .FILL x0080
10 .FILL x0100
11 .FILL x0200
12 .FILL x0400
13 .FILL x0800
14 .FILL x1000
15 .FILL x2000
16 .FILL x4000
```

(a) Write a subroutine `CLEAR` in LC-3 assembly language that clears a bit in R0 using the table above. The index of the bit to clear is specified in R1. R0 and R1 are inputs to the subroutine.

(b) Write a similar subroutine `SET` that sets the specified bit instead of clearing it.

Hint: You should remember to save and restore any registers your subroutine uses (the "callee save" convention). Use the `RET` instruction as the last instruction in your subroutine (R7 contains the address of where to return to.)

T3

Adapted from 8.11

The following program needs to be assembled and stored in LC-3 memory.

```

1      .ORIG x4000
2      AND R0,R0,#0
3      ADD R1,R0,#0
4      ADD R0,R0,#4
5      LD  R2,B
6      A  LDR R3,R2,#0
7      ADD R1,R1,R3
8      ADD R2,R2,#1
9      ADD R0,R0,#-1
10     BRnp A
11     JSR SHIFTR
12     ADD R1,R4,#0
13     JSR SHIFTR
14     ST  R4,C
15     TRAP x25
16     B  .BLKW 1
17     C  .BLKW 1
18     .END

```

(a) How many memory locations are required to store the assembled program?

(b) What is the address of the location labeled C?

(c) Before the program can execute, the location labeled B must be loaded by some external means. You can assume that happens before this program starts executing. You can also assume that the subroutine starting at location SHIFTR is available for this program to use. SHIFTR takes the value in R1, shifts it right one bit, and stores the result in R4.

After the program executes, what is in location C?

T4

Adapted from 8.13

Our code to compute n factorial worked for all positive integers n . Augment the iterative solution to FACT to also work for $0!$.

```

1  FACT   ST   R1,SAVE_R1
2         ADD  R1,R0,#0
3         ADD  R0,R0,#-1
4         BRz  DONE
5  AGAIN  MUL  R1,R1,R0
6         ADD  R0,R0,#-1 ; R0 gets next integer for MUL
7         BRnp AGAIN
8  DONE   ADD  R0,R1,#0 ; Move n! to R0
9         LD   R1,SAVE_R1
10        RET
11  SAVE_R1 .BLKW 1

```

T5

Adapted from 9.6 & 9.9

- (a) What problem could occur if a program does not check the *Ready* bit of the KBSR before reading the KBDR?
- (b) What problem could occur if the keyboard hardware does not check the KBSR before writing to the KBDR?
- (c) Which of the above two problems is more likely to occur? Give your reason.

T6

Adapted from P353 9.13

Some computer engineering students decided to revise the LC-3 for their senior project.

In designing the LC-4, they decided to conserve on device registers by combining the KBSR and the DSR into one status register: the IOSR (the input/output status register). IOSR[15] is the keyboard device ready bit and IOSR[14] is the display device ready bit.

What are the implications for programs wishing to do I/O? Is this a poor design decision?

T7

Adapted from 9.16

- (a) How many `TRAP` service routines can be implemented in the LC-3? Why?
- (b) How many accesses to memory are made during the processing of a `TRAP` instruction?

T8

Adapted from P354 9.19

The following LC-3 program is assembled and then executed. There are no assemble time or run-time errors. What is the output of this program? Assume all registers are initialized to 0 before the program executes.

```

1      .ORIG x3000
2      LEA R0, LABEL
3      STR R1, R0, #3
4      TRAP x22
5      TRAP x25
6 LABEL .STRINGZ "FUNKY"
7 LABEL2 .STRINGZ "HELLO WORLD"
8      .END

```

T9

Adapted from P355 9.21

Assume that an integer greater than 2 and less than 32,768 is deposited in memory location A by another module before the program below is executed.

```

1      .ORIG x3000
2      AND R4, R4, #0
3      LD R0, A
4      NOT R5, R0
5      ADD R5, R5, #2
6      ADD R1, R4, #2
7      ;
8 REMOD JSR MOD
9      BRz STORE0
10     ;
11     ADD R7, R1, R5
12     BRz STORE1
13     ADD R1, R1, #1
14     BR REMOD
15     ;
16 STORE1 ADD R4, R4, #1
17 STORE0 ST R4, RESULT
18     TRAP x25
19     ;
20 MOD   ADD R2, R0, #0
21     NOT R3, R1
22     ADD R3, R3, #1
23 DEC   ADD R2, R2, R3
24     BRp DEC
25     RET
26     ;
27 A     .BLKW 1
28 RESULT .BLKW 1
29     .END

```

In 25 words or fewer, what does the above program do?

T10

Adapted from P360 9.31

The program below, when complete, should print the following to the monitor:

ABCFGH

Insert instructions at (a)–(d) that will complete the program.

```

1      .ORIG x3000
2      LEA R1, TESTOUT
3  BACK_1 LDR R0, R1, #0
4          BRz NEXT_1
5          TRAP x21
6          ----- (a)
7          BRnzp BACK_1
8          ;
9  NEXT_1 LEA R1, TESTOUT
10 BACK_2 LDR R0, R1, #0
11          BRz NEXT_2
12          JSR SUB_1
13          ADD R1, R1, #1
14          BRnzp BACK_2
15          ;
16 NEXT_2 ----- (b)
17          ;
18 SUB_1 ----- (c)
19 K      LDI R2, DSR
20          ----- (d)
21          STI R0, DDR
22          RET
23 DSR    .FILL xFE04
24 DDR    .FILL xFE06
25 TESTOUT .STRINGZ "ABC"
26          .END

```

T11

Adapted from P362 9.33

Interrupt-driven I/O:

(a) What does the following LC-3 program do?

```

1      .ORIG x3000
2      LD R3, A
3      STI R3, KBSR
4      AGAIN LD R0, B
5          TRAP x21
6          BRnzp AGAIN
7  A      .FILL x4000
8  B      .FILL x0032
9  KBSR   .FILL xFE00
10          .END

```

(b) If someone strikes a key, the program will be interrupted and the keyboard interrupt service routine will be executed as shown below. What does the keyboard interrupt service routine do?

```

1      .ORIG x1000
2      LDI R0, KBDR
3      TRAP x21
4      TRAP x21
5      RTI
6  KBDR  .FILL xFE02
7          .END

```

(c) Finally, suppose the program of part a started executing, and someone sitting at the keyboard struck a key. What would you see on the screen?

(d) In part c, how many times is the digit typed shown on the screen? Why is the correct answer: "I cannot say for sure."

T12

Adapted from P364 9.43

Two students wrote interrupt service routines for an assignment. Both service routines did exactly the same work, but the first student accidentally used RET at the end of his routine, while the second student correctly used RTI.

There are three errors that arose in the first student's program due to his mistake. Describe any two of them.